

CUSTOMER PROCEDURE


Install DJI Terra and activate an offline license

For a processing PC with no Internet connection: software installation, license request, exchange with DJI and activation.



At a glance.

An offline license lets you use the paid features of DJI Terra on a computer that is never connected to the Internet. It is tied to that specific computer. The license file is prepared from any other computer with an Internet connection.



How the license file travels. PIM diagram.

Before you start.

The processing PC

- Windows 10 or later, 64-bit
- Intel Core i5 processor or higher
- NVIDIA graphics card with compute capability 6.1 or higher (preferably GeForce GTX 1050 Ti or higher), 4 GB of video memory or more
- 32 GB of RAM or more
- 200 GB of free space, preferably on an SSD
- Up-to-date graphics card driver

What you need

- The **exchange code** for your license, provided by Drone Parts Center
- A second computer connected to the Internet
- A USB drive to move files from one computer to the other
- The email address that will receive the license file


Important. The license is tied to the hardware of the processing PC. Once the license request has been created, do not change the motherboard, processor or hard drive: the license would become invalid.

1. Install DJI Terra.

1

Download the software

On the connected computer, open the official download page enterprise.dji.com/dji-terra/downloads and download the Windows version of DJI Terra (`.iso` file). Copy this file to the USB drive, then to the processing PC.



DJI Terra download page. Screenshot: DJI website, October 2026.

2

Open the ISO file and start the installation


In File Explorer, right-click the ISO file and choose **Open**: Windows displays it as a disc drive. Open this drive and double-click `Terra.exe` . If the ISO does not open, extract it with 7-Zip or WinRAR and run `Terra.exe` from the extracted folder.

Windows asks for permission to make changes: click **Yes**. The installation requires administrator rights.

3

Follow the setup wizard

Choose the language, the installation folder and the shortcuts you want, check the summary, then click **Install**. A black command window opens while the driver is being installed: this is normal. When it finishes, launch DJI Terra or restart the computer if the wizard prompts you to.



Language, folder, shortcuts, summary and installation. Screenshots: DJI Terra user manual.

2. Create the license request.

These steps are done **on the processing PC**, the one that will use the license.

4


Install CodeMeter

CodeMeter is the license manager used by DJI Terra. In the DJI Terra installation folder, open `CodeMeter > Installer`, run `CodeMeterRuntime.exe` and follow the instructions.

5

Import the Terra license template

Still in the installation folder, open **CodeMeter** > **LIF** and double-click **Terra_license.WibuCmLIF**. Wait for the confirmation message.




License template imported successfully. Screenshot: DJI Terra user manual.

6

Generate the request file (.WibuCmRaC)

Open **CodeMeter Control Center**, select the **Terra Container** and click **License Update**.




CodeMeter Control Center, License Update button. Screenshot: DJI Terra user manual.

7

Save the request

Choose **Create license request**, then **Next**. Specify the file location and name, then click **Commit**. Copy the resulting **.WibuCmRaC** file to the USB drive.



Choosing the action, then naming the request file. Screenshots: DJI Terra user manual.

3. Exchange the license with DJI.

This step is done **on the connected computer**.


8

Fill in the exchange page

Open terra-license.djiservice.org, **Single Device License Exchange** tab (the language can be changed at the top right), then enter:

- **Email:** the address that will receive the license file;
- **Exchange Type:** **First-time Exchange** for a first activation;
- **Exchange Code:** the exchange code provided by Drone Parts Center;
- **License File:** click **Upload** and choose the `.WibuCmRaC` file.

Click **Next** to confirm the exchange.



DJI Terra license exchange page. Screenshot: DJI website, October 2026.

9

Receive the license file


DJI sends the `.WibuCmRaU` license file as an email attachment to the address you entered. Save it to the USB drive.

4. Activate the license on the processing PC.

10

Import the license

Copy the `.WibuCmRaU` file to the processing PC, **the same one that created the request**, then double-click it. Wait for the message confirming that the update was successful.




License file imported successfully. Screenshot: DJI guide “Preparation Before Using DJI Terra”.

11

Log in offline

Launch DJI Terra and click **Offline Login**. The features of your license are available without an Internet connection.



Offline Login button. Screenshot: DJI guide “Preparation Before Using DJI Terra” (previous interface).

Upgrading from Terra Standard to Terra Flagship. On the exchange page, choose **Upgrade** as the exchange type, then enter the email address, the upgrade exchange code and the **Master ID**. The Master ID is in the first email received at activation; if you cannot find it, contact Drone Parts Center or DJI support.

Good to know.

- **Updates.** A perpetual license includes free updates for one year from its first binding. After that, a perpetual license upgrade is required to install new versions.
- **Changing computers or hardware.** If the license becomes invalid after a hardware change, you need to request a license unbinding from DJI support. A license for one device can be unbound once per calendar year.
- **Network features unavailable offline,** according to the DJI guide: GEO zone unlocking, map loading and location search; during mission flights with a drone, altitude is limited to 30 m and distance to 50 m.

Official DJI links.

DJI Terra download	enterprise.dji.com/dji-terra/downloads
Offline license exchange	terra-license.djiservice.org
Manual: activation and binding	terra.dji.com/user-manual/en/overview/activation-and-binding.html
System requirements	terra.dji.com/user-manual/en/overview/configuration.html
DJI Terra FAQ	enterprise.dji.com/dji-terra/faq

Need help?

Drone Parts Center

Authorized DJI Enterprise dealer
+32 67 88 37 37
info@drone-parts-center.com

PIM

Expert Drone Solutions
Rue Albert Einstein 20, 1400 Nivelles
pimdrone.eu

Document prepared by PIM based on the official DJI documentation consulted in October 2026. DJI screens may change: in the event of any discrepancy, the information displayed by DJI prevails. Screenshots are the property of DJI. DJI and DJI Terra are trademarks of SZ DJI Technology Co., Ltd.